

## 2-D Arrays, Macros and Procedures in PeANUt Assembler

- ref: [PeANUt Spec, sect 4]
- two-dimensional arrays
- macro definitions and usage
- the stack revisited
- procedures:
  - arguments
  - without local variables
- other issues:
  - revise 2008 MSE, Q1

## Two-dimensional Arrays

- multi-dimensional arrays are the main data structure in sci./eng. applications
- in C, implemented via row-major ordering:
  - i.e. 2-D element `ws[i][j]` is addressed as if 1-D element `ws[i*N+j]`, where `N` is length of a row (`ws[i]`)
- e.g. an array of strings (of length up to `N-1`)

```

                N      = 4      ;      #define N 4
                M      = 2      ;      #define M 2
                MN     = 8      ;      /* MN = M*N */
ws:      block  MN      ;      char ws[M][N];
i:      data   1      ;      int i = 1;
j:      data   2      ;      int j = 2;
                ;
                load   i      ;      ws[i][j] = 'x';
                mul    #N     ;
                add    j      ;
                storexr ;      /* XR=mem[i]*N+mem[j] */
                load   #'x'   ;
                store  *ws    ;
    
```

ws:	
	'x'
i:	1
j:	2

## PeANUt Macros

- important (yet simple) concept, widely used in the C language
- neither instructions nor procedures! Essentially, just a 'shorthand' or 'placeholder'
- macros are expanded by the assembler (as in C), not translated
  - i.e. exist only in the assembly language level
- definitions must be inserted at the top of a program
- can be good programming style, especially if they correspond to meaningful (high level language) operations
- are best for 'straight-line' code (don't use macros with branches etc.)

## PeANUt Macro Example: macro.ass

- definitions:

```
macro Get (x) ; read next char into x
    trap      #2 ; (read next char into AC)
    store     x ; (Memory[x] = AC)
endmacro

macro Set2 (x, e1, op, e2) ; perform x = e1 + e2
    load      e1 ; (AC = <value of e1>)
    op        e2 ; (AC = AC op <value of e2>)
    store     x ; (Memory[x] = AC)
endmacro
```

- Get(x) and Set2(x, e1, op, e2) can be called as follows:

```
Get      (ch) ; scanf ("%c", &ch);
Set2     (n, ch, sub, #'0'); n = ch - '0';
```

- these are expanded to

(see macro.lst, produced by assembler):

```
trap     #2
store    ch
load     ch
sub      #'0'
store    n
```

## PeANUt Macros – Beware!

- beware of the following:

```
Get ( ' 0 ' )  
Set2 ( n , sub , ch , # ' 0 ' )
```


- which is expanded to:

```
trap      #2  
store    ' 0 '      ; run-time error?  
load     sub       ; assembly error  
ch       # ' 0 '   ; assembly error  
store    n
```


- good use of macros can 'abstract' some low level details and can clarify the program's structure
- bad use of macros can obscure what is going on and be the origin of many errors

# The Stack and Function Calls

- a fundamental programming concept!!
  - hence hardware support is needed (e.g. SP register, stack addressing mode)
- uses a (reserved) part of (normal) memory called the stack
  - a stack is accessed *LIFO* (Last In, First Out), e.g. pile of books



- recall the stack can be efficiently implemented as the memory pointed to by SP:



- enables return of control to caller, as well as to pass parameters and return values

## Stack Addressing and Manipulation

- requires stack addressing mode (!):  $AOP = opspec + SP$
- normally,  $opspec \leq 0$

- recall example:

		⋮
259		
260	15	
261	-1	
SP → 262	40	
		⋮

```
load    !0      ; AOP = 262  OP = 40
mul     !-2     ; AOP = 260  OP = 15
store   !-3     ; AOP = 259  OP = 600
```

- the stack can be manipulated by software both implicitly:
  - via `call` and `ret` (SP is inc/decremented automatically)

and explicitly, using instructions like:


- `incsp #1,`
- `store !-1`



## Procedure Calls

- the procedure call convention determines the order of contents of the stack frame
- example C function declaration:

```
int P(int p1, int p2, ...) {
    int l1, l2, ...;
    ...
}
```



## Procedure Call – Example without Local Variables

- function definition (in InOut.asm; `Write(c)` is equivalent to `printf("%c", c)`)


```
ch      = -1      ; void Write(char ch) {
Write:  ;
        load      !ch      ; printf("%c",ch); /* AC=Mem[SP-1] */
        trap      #3      ; /* write AC to stdout */
        ret       ; } /* PC=Mem[SP]; SP=SP-1 */
```

- call from procedure-example1.asm:

```
        ; Write('a');
load    #'a'    ; /* Push('#'a') */ /* AC='a' */
incsp   #1      ; /* SP=SP+1 */
store   !0      ; /* Mem[SP]=AC */
call    Write   ; /* SP=SP+1;
                 ; Mem[SP]=PC;
                 ; PC=Write */
incsp   #-1     ; /* Pop(1) */ /* SP=SP-1 */
```

- remember: PC is incremented at the *beginning* of each instruction cycle

## Procedure call – Example without Local Variables: Stack



- for local variables, function must allocate/deallocate upon entry/exit *(later...)*